

# Installation Ubuntu 22.04 Server

## Installationsmedium

<https://releases.ubuntu.com/22.04/>

Während der Installation setze ich

- die Locale auf de\_de
- das Keyboard-Layout auf „German QWERTZ“
- Hostname

## LVM einrichten



## Handwerkszeug installieren

**aptitude**

```
# apt-get install aptitude
```

## VIMnox

```
# aptitude install vim-nox
```

## Midnight Commander

```
# aptitude install mc
```

## Net-Tools (ifconfig, etc.)

```
# aptitude install net-tools
```

## Timezone

Aktuell eingestellte Zeitzone:

```
# timedatectl
      Local time: Sun 2020-10-11 11:00:01 UTC
      Universal time: Sun 2020-10-11 11:00:01 UTC
      RTC time: Sun 2020-10-11 11:00:02
      Time zone: Etc/UTC (UTC, +0000)
System clock synchronized: yes
      NTP service: active
      RTC in local TZ: no
```

Zeitzone umstellen:

```
# timedatectl list-timezones|grep Berlin
Europe/Berlin
# timedatectl set-timezone Europe/Berlin
# timedatectl
      Local time: Sun 2020-10-11 13:02:31 CEST
      Universal time: Sun 2020-10-11 11:02:31 UTC
      RTC time: Sun 2020-10-11 11:02:32
      Time zone: Europe/Berlin (CEST, +0200)
System clock synchronized: yes
      NTP service: active
      RTC in local TZ: no
```

## NTP Client

</etc/systemd/timesyncd.conf>

```
# This file is part of systemd.
```

```
#
# systemd is free software; you can redistribute it and/or modify it
# under the terms of the GNU Lesser General Public License as
# published by
# the Free Software Foundation; either version 2.1 of the License, or
# (at your option) any later version.
#
# Entries in this file show the compile time defaults.
# You can change settings by editing this file.
# Defaults can be restored by simply deleting this file.
#
# See timesyncd.conf(5) for details.

[Time]
NTP=ptbtime1.ptb.de
FallbackNTP=ptbtime3.ptb.de ptbtime2.ptb.de
```

Momentane Systemzeit ansehen:

```
timedatectl
```

```
Local time: So 2018-11-25 11:26:59 CET
Universal time: So 2018-11-25 10:26:59 UTC
RTC time: So 2018-11-25 10:27:00
Time zone: Europe/Berlin (CET, +0100)
System clock synchronized: yes
systemd-timesyncd.service active: yes
RTC in local TZ: no
```

```
systemctl restart systemd-timesyncd
systemctl status systemd-timesyncd
● systemd-timesyncd.service - Network Time Synchronization
  Loaded: loaded (/lib/systemd/system/systemd-timesyncd.service; enabled;
  vendor preset: enabled)
  Active: active (running) since Sun 2018-11-25 11:29:00 CET; 1s ago
  Docs: man:systemd-timesyncd.service(8)
  Main PID: 16475 (systemd-timesyn)
  Status: "Synchronized to time server 192.53.103.108:123
  (ptbtime1.ptb.de)."
```

```
Tasks: 2 (limit: 2319)
  CGroup: /system.slice/systemd-timesyncd.service
          └─16475 /lib/systemd/systemd-timesyncd
```

```
Nov 25 11:29:00 backup systemd[1]: Starting Network Time Synchronization...
Nov 25 11:29:00 backup systemd[1]: Started Network Time Synchronization.
Nov 25 11:29:01 backup systemd-timesyncd[16475]: Synchronized to time server
192.53.103.108:123 (ptbtime1.ptb.de).
```

## Reaktivierung von ifupdown

Um netplan.io zu deaktivieren, muss lediglich das Paket ifupdown installiert werden. **Die Deinstallation von netplan.io ist nicht empfehlenswert**, insbesondere dann nicht, wenn die Deaktivierung via SSH vorgenommen wird. Nach der Deinstallation ist ein Zugriff via IP nicht mehr möglich. Es muss auf die Konsole ausgewichen werden!

```
aptitude install ifupdown
```

Im Bootloader muss ebenfalls das Laden von netplan unterdrückt werden:

[/etc/default/grub](#)

```
[...]  
GRUB_CMDLINE_LINUX="netcfg/do_not_use_netplan=true"
```

```
update-grub
```

Um das klassische Verhalten von ifupdown wiederherzustellen, muss ebenfalls systemd-networkd ausgeschaltet werden. Dies geschieht folgendermaßen:

```
systemctl disable systemd-networkd.service  
systemctl mask systemd-networkd.service  
systemctl stop systemd-networkd.service
```

Die Netzwerkkonfiguration sollte nun komplett aus der interfaces-Datei übernommen werden. Eine Ausnahme stellen die DNS-Server dar. Damit diese ebenfalls aus interfaces übernommen werden, muss systemd-resolved ausgeschaltet und resolvconf aktiviert werden!

```
aptitude install resolvconf
```

```
systemctl disable systemd-resolved.service  
systemctl stop systemd-resolved.service  
systemctl mask systemd-resolved.service
```

```
systemctl disable systemd-networkd-wait-online.service  
systemctl stop systemd-networkd-wait-online.service  
systemctl mask systemd-networkd-wait-online.service
```

Jetzt die `/etc/network/interfaces` final editieren, sonst kein Zugriff mehr!

```
reboot
```

From:

<https://wikinet.webby.hetzel-netz.de/> - **Sebastians IT-Wiki**

Permanent link:

[https://wikinet.webby.hetzel-netz.de/ubuntu:22-04\\_server\\_install?rev=1667648643](https://wikinet.webby.hetzel-netz.de/ubuntu:22-04_server_install?rev=1667648643)

Last update: **2022/11/05 12:44**

