

Navidrome Musik-Streaming auf Ubuntu Server

**Navidrome**

Navidrome Server Software

<https://www.navidrome.org/>

<https://www.navidrome.org/docs/installation/linux/>

<https://github.com/navidrome/navidrome/releases>

Installation

Volumes und Partitionierung

VNC - vm

Storage configuration [Help]

FILE SYSTEM SUMMARY

MOUNT POINT	SIZE	TYPE	DEVICE	TYPE
[/	15.000G	new ext4	new LVM logical volume	▶]
[/boot	1.000G	new ext4	new partition of local disk	▶]
[/home	5.000G	new ext4	new LVM logical volume	▶]
[/srv	5.947T	new ext4	new LVM logical volume	▶]
[/var	15.000G	new ext4	new LVM logical volume	▶]
[SWAP	18.000G	new swap	new LVM logical volume	▶]

AVAILABLE DEVICES

No available devices

[Create software RAID (md) ▶]
[Create volume group (LVM) ▶]

USED DEVICES

DEVICE	TYPE	SIZE
[vg0 (new)	LVM volume group	5.999T ▶]
lv-swap	new, to be formatted as swap	18.000G ▶]
lv-root	new, to be formatted as ext4, mounted at /	15.000G ▶]
lv-home	new, to be formatted as ext4, mounted at /home	5.000G ▶]
lv-var	new, to be formatted as ext4, mounted at /var	15.000G ▶]
lv-srv	new, to be formatted as ext4, mounted at /srv	5.947T ▶]
[/dev/vda	local disk	6.000T ▶]
partition 1	new, BIOS grub spacer	1.000M ▶]
partition 2	new, to be formatted as ext4, mounted at /boot	1.000G ▶]
partition 3	new, PV of LVM volume group vg0	5.999T ▶]

[Done]
[Reset]
[Back]

/dev/sda1	EFI	/boot/efi	ext4
/dev/sda2	/boot		ext4
/dev/sda3	LVM PV		

```
└─ vg0
   └─ lv-swap    swap
   └─ lv-root    /
   └─ lv-home    /home
   └─ lv-var     /var
   └─ lv-srv     /srv
```

From:

<https://wikinet.webby.hetzel-netz.de/> - **Sebastians IT-Wiki**

Permanent link:

<https://wikinet.webby.hetzel-netz.de/ubuntu:navidrome?rev=1770118784>

Last update: **2026/02/03 12:39**

